

Getting Started inpO2

**ALL YOU NEED TO KNOW TO GET STARTED ON
INPO2, EVERY STEP OF THE WAY.**

- How to **install** your new software
- How to **activate** your inpO2 dongle
- How to **upgrade**
- How to get professional **support**

MINIMUM REQUIREMENTS

Please see the back of your DVD case or the Release Notes for all details.

Table of Contents

Installation Steps for Windows.	p. 3
Installation Steps for Mac.....	p. 4
Licence Activation for Windows and Mac	p. 5
Licence Activation Steps.....	p. 5
Upgrading	p. 6
Support	p. 6

INSTALLATION STEPS

FOR WINDOWS



Before starting the installation, ensure that your USB dongle is NOT connected to your computer.

Step 1: Double-click the "Setup.exe" installation file.

Step 2: Follow the instructions of the Installer.

Step 3: At the end of the inp02 installation, the HASP driver installer will be launched. This installation is required for the proper functioning of the USB hardware key (dongle). Make sure the dongle is not connected before the process is completed.

Once the process is completed, inp02 will be found in Acrobat's plug_ins folder.

You can find all inp02 documentation in the Dynagram sub-folder.

Step 4: The next step is to activate your license (see the activation procedure on page 5).

INSTALLATION STEPS

FOR MAC



Before starting the installation, ensure that your USB dongle is NOT connected to your computer.

Step 1: Double-click the "Install inp02" installation file.

Step 2: Follow the instructions of the Installer.

Step 3: If you have more than one instance of Adobe Acrobat on your computer, select the one for which you want to install inp02 plug in.

Step 4: At the end of the inp02 installation, the HASP driver installer will be launched. This installation is required for the proper functioning of the USB hardware key (dongle). Make sure the dongle is not connected before the process is completed.

Once the process is completed, inp02 will be found in the plug-ins folder that you have selected.

Step 5: The next step is to activate your license (see the activation procedure on page 5).

LICENCE ACTIVATION

FOR WINDOWS AND MAC

IMPORTANT: In order to activate your inp02 license, you need to send your USB dongle information to Dynagram or your distributor.

US & Canada - Send an email to activation@dynagram.com with your complete identification and dongle number.

Other countries - Contact your reseller or distributor.

Turn to page 6 for the [License Activation Steps](#).

NOTE: inp02 is a dongle-protected application. The inp02 dongle is cross-platform, hence it can be connected to a PC or a Macintosh computer.

The USB dongle needs to be connected to your computer and its red light must be on, meaning it is active and installed properly. If the inp02 dongle is not connected to a USB port on your computer when you start Adobe Acrobat, the plug-in will simply not load and the inp02 menu will not appear in Acrobat's menu bar.

To see your license and dongle status, choose About inp02 from inp02's menu.

LICENCE ACTIVATION STEPS

- Step 1:** Connect the dongle to a USB port of your computer.
- Step 2:** Launch Acrobat.
- Step 3:** In Acrobat, choose License > Create License Request from the inp02's menu.
- Step 4:** Browse and save the c2v (customer to vendor) file on your computer. Then, fill out the registration form at: <http://www.dynagram.com/website/register.asp>. You will be prompted to upload your c2v file at the end of the registration form. If you purchased your inp02 product from a third party, please send your activation request and c2v file directly to your distributor.
- Step 5:** Upon receipt of your activation request, Dynagram or your distributor will send you back a v2c (vendor to customer) file that you need to load into inp02 dongle to activate the license:
- Step 6:** Ensure that your dongle is still connected and choose License... > Install License... from inp02's menu.
- Step 7:** Browse to the v2c file on your computer and click Open.
- Step 8:** Relaunch Acrobat to activate inp02 plug-in.

You do not need to repeat these steps unless you want to upgrade your license.

UPGRADING

The steps needed to upgrade your inp02 license are the same as for the initial activation, by the exchange of c2v and v2c files (see page 5).

It is important to wait for the reception of the v2c file before you install the upgrade otherwise you will not be able to use the product in the meantime, unless you revert to your previous version installation.

SUPPORT

To start your training on inp02 imposition software, see the **PDF documents in the *Dynagram* folder.**

The complete User's Manual is also available within Acrobat's Help menu with all search tools and hypertext links.

If you should need technical support, please fill out the support request form at: **www.dynagram.com/support.**

US & Canada

Tel.: 418-266-1275

Fax: 418-694-2048

E-mail: support@dynagram.com

Other Countries

Contact your distributor or reseller

Any questions?

Visit our website or contact your dealer today!

www.dynagram.com

 **Dynagram**

We make your work flow

© Copyright 2006-2012 Dynagram. All rights reserved.
inp02® is a registered trademark of Dynagram. Adobe® and Acrobat® are either registered trademarks or trademarks of Adobe Systems Incorporated in the United States and/or other countries.

Other brand or product names are trademarks or registered trademarks of their respective owners.
Printed in Canada.